

QCTool V6.x

Installation Instructions

Serial Number Installation ONLY

QCTool offers data processing and quality control for small and very large data files as well as gridding and mapping.

QCTool offers import of general XYZ ASCII column format files in various forms plus Excel .csv, BINARY XYZ, Geosoft .gbr, Geosoft .gdb;, Marine Magnetics; Scintrex CGx, magnetometer and IPR12 formats; GEM magnetometer and VLF formats and as well as formats for Geonics, GSSI, CMD, GDD, Micro-G, Zonge, SeaSpy, Stratagem, Phoenix, .usf format, SEG Y, and a large number of other formats including grid, borehole, observatory and DEM formats.

You will have been provided with a serial number.

Do not lose this serial number and do not abuse it. You have a limited number of registrations.
The serial number is your license.

QCTool offers an update process through the internet. To find this link, look under "HELP" or via the START menu to the QCTool group.

If using a CD to install:

Insert the CD into your CDRom.

If AutoRun is configured on your computer, the installation will begin automatically

If not, Run CD_Drive:\ QCTool_Setup.exe

otherwise RUN the downloaded installation executable.

--- The installer must have administrative privileges.

After installation, it is recommended to check the following environment variable:

Access environmental variables through Control Panel / System / Advanced

Add "c:\Program Files\QCTool\bin" to the Path variable

Note: If you have installed QCTool into a directory other than "c:\Program Files\QCTool" (the default directory) ensure that you use that path in the above step.

You must now re-boot your computer.

Moving a License to Another Computer

First, deregister the license on the computer you no longer wish to use by selecting "Deregister QCTool" from the Start menu or from HELP within QCTool. Then, install and register on the new computer.

IMPORTANT: Instructions can be found in QCTool under HELP. Manuals and Tutorials may be found after installation in QCTool folders on your hard drive or may be downloaded from the web pages.

Please contact us if you have any questions: QCTool Support Department
Email:info@qctool.ca